

Sparvio Toolbox Windows installation

Unzip the toolbox zip file to a directory of your choice. Some additional software packages may be needed, as listed below.

STM32 COM port driver

This is not needed for most systems so only install it if SA1 is not detected. Compatible with Windows 98SE, 2000, XP, Vista, 7, and 8.x.

Download and run the installation of Virtual COM port driver matching your system:

System	Link
Windows 7, 32-bit	http://sparv.io/VCP_V1.5.0_Setup_W7_x86_32bits.exe
Windows 8/10, 32-bit	http://sparv.io/VCP_V1.5.0_Setup_W8_x86_32bits.exe
Windows 7, 64-bit	http://sparv.io/VCP_V1.5.0_Setup_W7_x64_64bits.exe
Windows 8/10, 64-bit	http://sparv.io/VCP_V1.5.0_Setup_W8_x64_64bits.exe

Python 3

Sparvio Toolbox is compatible with Python 3.7 and later.

For example use Python 3.9.11: <https://www.python.org/downloads/release/python-3911/>

Then install required Python packages with this line (as a single line)

```
python -m pip install pyserial influxdb requests flask flask-socketio  
jedi prompt_toolkit pygments aiohttp aiohttp_jinja2
```

InfluxDB

Install InfluxDB (64-bit):

1. Download https://dl.influxdata.com/influxdb/releases/influxdb-1.7.1_windows_amd64.zip ¹
2. unzip the directory `influxdb-x.x.x` in the downloaded file where you want the application, for example inside `C:\Program Files\`.
3. Suggestion for convenience: Create a Windows shortcut to `influxd.exe`. Right-click on the Windows desktop, choose New -> Shortcut and enter the full path to the executable, for example `C:\Program Files\influxdb-1.7.1\influxd.exe`
4. Start `influxd.exe` or the shortcut.

Grafana

1. Download Grafana: <https://dl.grafana.com/oss/release/grafana-8.5.15.windows-amd64.zip> ²
If needed, more installation info is here: <https://grafana.com/docs/grafana/v8.5/installation/windows/#install-standalone-windows-binary>
2. Unzip the directory `grafana-8.5.15` in the downloaded file to `My Documents` -- **don't** place under `C:\Program Files` as the application would not have the permissions it needs to modify its files.

3. Suggestion for convenience: Create a Windows shortcut to `bin\grafana-server.exe` under the grafana directory. Right-click on the Windows desktop, choose New -> Shortcut and enter the full path to the executable, for example `C:\Users\xxxxx\My Documents\grafana-8.5.15\bin\grafana-server.exe` (replace xxxxx by your own user name).
4. Run `grafana-server.exe` or the shortcut. If Windows warns about "unrecognized application", choose "More info" and "Run anyway".

Next, configure Grafana as detailed in the user manual.

-
- 1 The newer version 1.8.10 (https://dl.influxdata.com/influxdb/releases/influxdb-1.8.10_windows_amd64.zip) seems to work too but is not tested extensively. Version 2 requires other installation instructions, so it's not recommended.
 - 2 The newer Grafana 9 doesn't seem to work with InfluxDB 1.8.